

# **UrbanTexture**

## **User Manual**

**Version 1.0.0**

November, 2021

UrbanComp@HPSCIL

<https://www.urbancomp.net/>

# 1. Product Introduction

## 1.1 UrbanTexture Product

UrbanTexture V1.0.0 is used to calculate the distribution curve of buildings around a geographic location and supports the extraction of the curves' mathematical features. The features acquired by UrbanTexture can be used to express the land surface temperature.

UrbanTexture also supports interfaced input and output data, Geohash-based spatial analysis, curve visualization and feature extraction.


## 1.2 Target Users

Researchers and urban planners in the field of urban planning.

## 1.3 Installation

Please **unzip** the software package to the full English file path. Open the unzipped folder, click “**setup.exe**”, and follow the wizard to complete the installation. Click “**UrbanTexture.exe**” or shortcut to use the software.

## 1.4 User Interface




## 1.5 Software Control Panel Description

### 1.5.1 Menu Bar


The menu bar of UrbanTexture includes 6 parts:

**“Open CSV”, “Export Image”, “Run RDF”, “Generate Graph”, “Feature Extraction” and “About US”.**




### 1.5.2 Toolbar

This part is consist of **“CSV”, “Export Image”, “RDF”, “GenerateGraph”, “Feature Extraction” and “AboutUs”.**





## 1.5.3 Data Visualization Panel




## 1.5.4 Exception Prompt Dialog Box



In “Generate RDF”, if no parameter is selected or an incorrect parameter is selected, the following error message will be displayed:







If the output path of the CSV file is not selected, a message will be displayed:




Click “**Generate Graph**” icon  or “**Feature Extraction**”  icon is displayed, the interface for selecting parameters will be displayed. If you do not select the CSV file or the number of lines, the following error message will be displayed:




In “**Generate Graph**”, if you enter the number of building lines out of range, you will get an error message:




In “**Generate Graph**”, you cannot select the same number of columns when selecting parameters.




In “**Generate Graph**”, FID is an integer, latitude and longitude is a decimal, you cannot select the wrong column to enter value.



In “**Generate Graph**”, the number of building lines you enter cannot exceed the maximum file size.




In “**Generate Graph**” and “**Feature Extraction**”, you must select a compliant CSV file to draw curves or calculate characteristic values of curves.




## 2. Data Display Function

### 2.1 Basic Function



#### 2.1.1 Import CSV Files

Click “**CSV**” icon  on the toolbar of the main window to go to the dialog box for opening the CSV file. Select the CSV file to be opened and import it.


You can add multiple CSV files for viewing.



## 2.1.2 Generate TextureRDF

Click the icon  on the toolbar or the “Run RDF” button  on the menu bar of the main interface, and the following interface will appear.

The parameter information is described in details on the first page. You can also see the parameter information at the end of this section.





The screenshot shows the 'generateTextureRDF' application window with the 'Parameter Settings' tab selected. The interface includes several input fields and buttons for configuring the texture generation process.

**Parameter Settings**

CSV1 for input

The location information

- Column number of FID: 0
- Column number of longitude: 0
- Column number of latitude: 0
- Column number of unit area: 0

The height information

- ☒ Column number of Total floor height: 0
- ☐ Column number of floors: 0
- Floor height: 2.00
- ☐ Column number of DEM: 0

Information used for computation

- Dome step radius: 0.00
- Total radius of dome: 0.00
- Hash level: 0
- ☐ Whether to normalize



CSV2 for input

Output CSV: result.csv

Run

Back

Click “CSV1 for input” , “ CSV2 for input ”and ”Output CSV” buttons to jump to **Explorer** and select the file to enter. If the selection is successful, you will be prompted.



Enter all parameters that conform to the rules, then click "**Run**". The parameters you have entered will be visualized in the small window in the lower left corner:

**generateTextureRDF**

Parameter Description    Parameter Settings

CSV1 for input    /s/jiony/Desktop/UrbanTexture/data/eerduosi.csv

The location information

Column number of FID    0

Column number of longitude    2    Column number of latitude    3

Column number of unit area    4

The height information

☐ Column number of Total floor height    0

☒ Column number of floors    1    Floor height    3.00

☐ Column number of DEM    0

Information used for computation

Dome step radius    500.00

Total radius of dome    5000.00

Hash level    8    ☐ Whether to normalize

CSV2 for input    /ony/Desktop/UrbanTexture/data/input\_lat\_lon.csv


Output CSV    result.csv

FID\_Column is 0  
LAT\_Column is 2  
LNG\_Column is 3  
PerArea\_Column is 4  
you choose is floor number, and its col is 1  
every floor's height is 3

Run

Back

Click the “CSV” icon to display the output file results



### 2.1.2.1 Column number of FID

Range [0, maximum column number), represents the data information of FID and must be integers.

### 2.1.2.2 Column number of longitude

Range [0, maximum column number), represents the data information of longitude, and must be decimals.

### 2.1.2.3 Column number of latitude

Range [0, maximum column number), represents the data information of latitude and must be decimals.

### 2.1.2.4 Column number of total floor height

Range [0, maximum column number), represents the data information of total floor height and must be decimals.

### **2.1.2.5 Column number of the number of floors**

Range [0, maximum column number), represents the data information of floors and must be integers.

### **2.1.2.6 Floor height**

Greater than zero, represents the data information of the height of each floor;

Note that you can only select either the floor height column number or the height of each floor for parameter input, and if you select the latter, you also need to set the height of each floor.

### **2.1.2.7 Column number of DEM**

Range[0, maximum column number), and the column data must be decimals.

### **2.1.2.8 Dome step radius**

Greater than zero.

### **2.1.2.9 Total radius of dome**

Greater than the dome step radius.


### **2.1.2.10 Hash level**

Range[0, 10], describes the normalized level.


### **2.1.2.11 Whether to normalize**

Check it if you want your data to be normalized.


## **2.1.3 Curve Drawing and Output**


Click on the "Generate Graph" icon  or button [Generate Graph](#) in the

toolbar, select the CSV file that you want to generate the curve, and fill in the number of lines for the corresponding building.




Click "**Confirm**" button to generate the corresponding curve in the interface:







If necessary, you can repeat the above steps to add more curves for comparison.


For more accurate comparison, you can also click the legend corresponding to the curve in the chart to hide the curve for more intuitive analysis.





After the curve is drawn, click the **"Export Image"** icon  or button


**Export Image** and select the image storage path to download the curve.





## 2.1.4 Curve Feature Extraction


After the curve is drawn, the characteristics of the curve can be extracted to




provide a reference for the study. Click the **"Feature Extraction"** icon  or button **Feature Extraction**, select the curve CSV file you want to extract, and select the number of building lines to see the details of each feature value in the lower right corner of the interface.



If you need to save the characteristic value details of the current curve, **click** the **"save as text file"** button to download it. If the download is successful, you will be prompted.



Now you can view it.



```
Results of feature extraction.txt - 记事本
文件(F) 编辑(E) 格式(O) 查看(V) 帮助(H)
Curve feature extraction:
mean=6.4e-05
Median = 7.3e-05
Standard deviation = 1.85418e-05
Standard deviation of Norm Time Series = 0.276744
Range = 6.7e-05
Kurtosis = 38.857
skewness = -13.2204
Burstiness statistic = -0.550729
BCoefficient of variation = 0.289716
BCoefficient of variation = 0.289716
Negative log likelihood = -0.000618755
RMSE of linear fit =1.48995e-05
RMSE of binomial fit =6.03077e-06
RMSE of trinomial fit =4.27159e-06

The mean of remove the 10% maximum and 10% minimum = 6.6875e-05
第 1 行, 第 1 列 100% Unix (LF) UTF-8
```

### 3. Copyright notice and contact information

If you encounter problems in use, please contact us in time.

UrbanTexture

Contact details:

Yao YAO (yaoy@cug.edu.cn)

Guangxiang Zhou (zhougx9981@cug.edu.cn)

Chenxi Liu (20191001508@cug.edu.cn)

Jiangling Wei (jiongyWei@163.com)

Zhenhui Sun (vadersun@163.com)

Website: <http://www.urbancomp.net>

Copyright 2021 UrbanComp All Rights Reserved